


Instruction Manual

Smartinterface Drak

(Voor Mares Puck, Puck Air, Puck Wrist, Nemo Wide, Nemo Air)



Instruction Manual - Smartinterface Drak


Do not connect the interface to your computer yet. A driver is required first, which is automatically installed with the read out software.

The software is available for download from Mares free of charge.


You can find Mares on the internet at: <http://www.mares.com>.

Select your language and search for the current software version for your dive computer. First click on "Downloads", then click the button „Download the Dive Organizer“.

Smartinterface Drak




- 1.0 Download the Web Installer or choose Full Setup. Once the download is complete, start the installation and follow the instructions.




Do not connect the interface yet!

Smartinterface Drak






- 1.1 For installing the application and all drivers, choose the option „Custom“ and select Icon Driver and Silicon Labs Drivers.





- 1.2 Select the default destination folder or enter your own.


Smartinterface Drak



Smartinterface Drak



1.3 The Dive Organizer has now been installed. Run the Dive Organizer by setting the checkmark or run it via the Start button (see image below).




Smartinterface Drak



Login window showing the mares dive organizer logo and a circular seal for DAN RESEARCH 100% DAN DLT. The login form includes fields for Username and Password, a green plus sign button, and a green checkmark button.

2.0 First add a new user by clicking the green plus-sign.



New user registration window with the following fields:

- First Name*
- Last Name*
- User name*
- Language (English)
- Start dives with no. (1)
- Units of measure (m | kg | bar | | °C)
- Password
- Confirm password
- Secret question*
- Secret answer*

The items marked with * are required profile fields and need to be filled out.

☐ Additional info


Green checkmark and red X buttons at the bottom right.

2.1 Fill in all mandatory fields (marked with a star) and select your units.

Smartinterface Drak



2.2 Log in with the username you just created and create a password.




2.3 Dive Organizer is now starting with the user you logged in.

Smartinterface Drak



3.0 You can now connect your new interface to the computer.



3.1 After you connected the interface, Windows will install the drivers. After a short while, a message will appear confirming the installation.




3.2 The interface has been recognised by the computer and a green LED is lit.


If this is not the case, restart the Dive Organizer.

When connecting the interface to the dive computer, the green LED will light up for about 2 seconds.

Smartinterface Drak



4.0 After logging in, select „Select Drak Computer | Matrix“ from the „Computer“ drop down menu.



4.1 Select your dive computer, e.g. „Nemo Air“.



4.2 Follow the instructions for connecting the interface.


Please don't forget to set your dive computer to the transfere mode.

Note: On the next page you'll find an image on how to connect the interface to your dive computer.


Smartinterface Drak



5.0 With a smartinterface the direction you choose to connect it with your dive computer doesn't matter. When connected, the LED will shine red.




5.1 Congratulations! Your diving computer is now successfully connected to your computer with the smartinterface.





5.2 In the next screen you can fill in some information about your dive computer.

Smartinterface Drak




6.0 Logbook download: The „Computer“ button in the menu has now been replaced by the name of your diving computer. Select it and choose „Download Logbook“

All dives will now be downloaded.




6.1 In the next screen you see an overview of all the dives in the logbook.



6.2 Select the dives you want to import and click on the middle icon to start the download.


Smartinterface Drak



7.0 Your selected dives have now been imported into the Dive Organizer.

Content

1.0	Download the Web Installer or choose Full Setup. Once the download is complete, start the installation and follow the instructions.	2
1.1	For installing the application and all drivers, choose the option „Custom“ and select Icon Driver and Silicon Labs Drivers.	3
1.2	Select the default destination folder or enter your own.	3
1.3	The Dive Organizer has now been installed. Run the Dive Organizer by setting the checkmark or run it via the Start button (see image below).	5
2.0	First add a new user by clicking the green plus-sign.	6
2.1	Fill in all mandatory fields (marked with a star) and select your units.	6
2.2	Log in with the username you just created and create a password.	7
2.3	Dive Organizer is now starting with the user you logged in.	7
3.0	You can now connect your new interface to the computer.	8
3.1	After you connected the interface, Windows will install the drivers. After a short while, a message will appear confirming the installation.	8
3.2	The interface has been recognised by the computer and a green LED is lit. If this is not the case, restart the Dive Organizer. When connecting the interface to the dive computer, the green LED will light up for about 2 seconds.	8
4.0	After logging in, select „Select Drak Computer I Matrix“ from the „Computer“ drop down menu.	9
4.1	Select your dive computer, e.g. „Nemo Air“.	9
4.2	Follow the instructions for connecting the interface.	9
5.0	With a smartinterface the direction you choose to connect it with your dive computer doesn't matter. When connected, the LED will shine red.	10
5.1	Congratulations! Your diving computer is now successfully connected to your computer with the smartinterface.	10
5.2	In the next screen you can fill in some information about your dive computer.	10
6.0	Logbook download: The „Computer“ button in the menu has now been replaced by the name of your diving computer. Select it and choose „Download Logbook“. All dives will now be downloaded.	11
6.1	In the next screen you see an overview of all the dives in the logbook.	11
6.2	Select the dives you want to import and click on the middle icon to start the download.	11
7.0	Your selected dives have now been imported into the Dive Organizer.	12



Imprint Technisches Büro Kühnhold
Ehestorfer Weg 155
21075 Hamburg


<http://www.smartinterface.de> · info@smartinterface.de

Copyright All images and text in this instruction manual, as well as the instruction manual itself are copyright protected, any further use must be approved in writing by www.smartinterface.de.

Copyright and labeling All brands and trademarks specified within the description and, where applicable, protected by a third party are subject without restriction to the terms and conditions of the respectively valid right to use a symbol and the ownership rights of each registered owner.
The mere mention thereof shall not be construed to represent that the trademarks are not protected by third party rights! The brand names and trademarks used in this documentation are the property of the respective rights owners and are used here only for descriptive purposes.

Disclaimers The devices, tools and interfaces were thoroughly tested prior to the delivery. Connection, use and operation shall be at your own risk. No liability shall be assumed for damage or loss of data or lack of waterproofness.

Recycling European Union – Disposal information: This symbol indicates that this product must be disposed of pursuant the valid legal provisions and separated from domestic waste. Bring this product to an official collection point for disposal. Products can be brought to some collection points for disposal free of charge. Separate collection and recycling conserves raw material reserves and ensures compliance with all regulations for the protection of health and the environment when recycling the product.



CE  **RoHS**✓
WEEE-Reg.-Nr. DE82497460